

Package: condMVNorm (via r-universe)

August 31, 2024

Title Conditional Multivariate Normal Distribution

Version 2020.1

Date 2020-03-17

Description Computes conditional multivariate normal densities, probabilities, and random deviates.

Imports stats

Depends R(>= 3.0), mvtnorm

License GPL-2

Author Ravi Varadhan [aut, cre]

Maintainer Ravi Varadhan <ravi.varadhan@jhu.edu>

NeedsCompilation no

Date/Publication 2020-03-18 15:50:16 UTC

Repository <https://rvaradhan.r-universe.dev>

RemoteUrl <https://github.com/cran/condMVNorm>

RemoteRef HEAD

RemoteSha 0fd320baf2c4afc59500b6583725912e6aa6c98f

Contents

cmvnorm	2
condMVN	3
pcmvnorm	4
Index	7

Description

These functions provide the density function and a random number generator for the conditional multivariate normal distribution, [Y given X], where $Z = (X, Y)$ is the fully-joint multivariate normal distribution with mean equal to mean and covariance matrix sigma.

Usage

```
dcmvnorm(x, mean, sigma, dependent.ind, given.ind,
  X.given, check.sigma=TRUE, log = FALSE)
rcmvnorm(n, mean, sigma, dependent.ind, given.ind,
  X.given, check.sigma=TRUE,
  method=c("eigen", "svd", "chol"))
```

Arguments

x	vector or matrix of quantiles of Y. If x is a matrix, each row is taken to be a quantile.
n	number of random deviates.
mean	mean vector, which must be specified.
sigma	a symmetric, positive-definite matrix of dimension n x n, which must be specified.
dependent.ind	a vector of integers denoting the indices of dependent variable Y.
given.ind	a vector of integers denoting the indices of conditioning variable X. If specified as integer vector of length zero or left unspecified, the unconditional distribution is used.
X.given	a vector of reals denoting the conditioning value of X. This should be of the same length as given.ind
check.sigma	logical; if TRUE, the variance-covariance matrix is checked for appropriateness (symmetry, positive-definiteness). This could be set to FALSE if the user knows it is appropriate.
log	logical; if TRUE, densities d are given as log(d).
method	string specifying the matrix decomposition used to determine the matrix root of sigma. Possible methods are eigenvalue decomposition ("eigen", default), singular value decomposition ("svd"), and Cholesky decomposition ("chol"). The Cholesky is typically fastest, not by much though.

See Also

[pcmnorm](#), [pnmnorm](#), [dmvnorm](#), [qmvnorm](#)

Examples

```

# 10-dimensional multivariate normal distribution
n <- 10
A <- matrix(rnorm(n^2), n, n)
A <- A %*% t(A)

# density of Z[c(2,5)] given Z[c(1,4,7,9)]=c(1,1,0,-1)
dcmvnorm(x=c(1.2,-1), mean=rep(1,n), sigma=A,
  dependent.ind=c(2,5), given.ind=c(1,4,7,9),
  X.given=c(1,1,0,-1))

dcmvnorm(x=-1, mean=rep(1,n), sigma=A, dep=3, given=c(1,4,7,9,10),
  X=c(1,1,0,0,-1))

dcmvnorm(x=c(1.2,-1), mean=rep(1,n), sigma=A, dep=c(2,5),
  given=integer())

# gives an error since `x' and `dep' are incompatible
#dcmvnorm(x=-1, mean=rep(1,n), sigma=A, dep=c(2,3),
# given=c(1,4,7,9,10), X=c(1,1,0,0,-1))

rcmvnorm(n=10, mean=rep(1,n), sigma=A, dep=c(2,5),
  given=c(1,4,7,9,10), X=c(1,1,0,0,-1),
  method="eigen")

rcmvnorm(n=10, mean=rep(1,n), sigma=A, dep=3,
  given=c(1,4,7,9,10), X=c(1,1,0,0,-1),
  method="chol")

```

condMVN

*Conditional Mean and Variance of Multivariate Normal Distribution***Description**

These functions provide the conditional mean and variance-covariance matrix of $[Y \text{ given } X]$, where $Z = (X, Y)$ is the fully-joint multivariate normal distribution with mean equal to mean and covariance matrix σ .

Usage

```
condMVN(mean, sigma, dependent.ind, given.ind, X.given, check.sigma=TRUE)
```

Arguments

mean	mean vector, which must be specified.
sigma	a symmetric, positive-definite matrix of dimension $n \times n$, which must be specified.
dependent.ind	a vector of integers denoting the indices of dependent variable Y .

<code>given.ind</code>	a vector of integers denoting the indices of conditioning variable X. If specified as integer vector of length zero or left unspecified, the unconditional density is returned.
<code>X.given</code>	a vector of reals denoting the conditioning value of X. This should be of the same length as <code>given.ind</code>
<code>check.sigma</code>	logical; if TRUE, the variance-covariance matrix is checked for appropriateness (symmetry, positive-definiteness). This could be set to FALSE if the user knows it is appropriate.

See Also

[dcmvnorm](#), [pcmvnorm](#), [pmvnorm](#), [dmvnorm](#), [qmvnorm](#)

Examples

```
# 10-dimensional multivariate normal distribution
n <- 10
A <- matrix(rnorm(n^2), n, n)
A <- A %%% t(A)

condMVN(mean=rep(1,n), sigma=A, dependent=c(2,3,5), given=c(1,4,7,9),
  X.given=c(1,1,0,-1))

condMVN(mean=rep(1,n), sigma=A, dep=3, given=c(1,4,7,9), X=c(1,1,0,-1))

condMVN(mean=rep(1,n), sigma=A, dep=3, given=integer())
# or simply the following

condMVN(mean=rep(1,n), sigma=A, dep=3)
```

pcmvnorm

Conditional Multivariate Normal Distribution

Description

Computes the distribution function of the conditional multivariate normal, [Y given X], where $Z = (X, Y)$ is the fully-joint multivariate normal distribution with mean equal to mean and covariance matrix sigma.

Usage

```
pcmvnorm(lower=-Inf, upper=Inf, mean, sigma,
  dependent.ind, given.ind, X.given,
  check.sigma=TRUE, algorithm = GenzBretz(), ...)
```

Arguments

lower	the vector of lower limits of length n.
upper	the vector of upper limits of length n.
mean	the mean vector of length n.
sigma	a symmetric, positive-definite matrix, of dimension n x n, which must be specified.
dependent.ind	a vector of integers denoting the indices of the dependent variable Y.
given.ind	a vector of integers denoting the indices of the conditioning variable X. If specified as integer vector of length zero or left unspecified, the unconditional distribution is used.
X.given	a vector of reals denoting the conditioning value of X. This should be of the same length as given.ind
check.sigma	logical; if TRUE, the variance-covariance matrix is checked for appropriateness (symmetry, positive-definiteness). This could be set to FALSE if the user knows it is appropriate.
algorithm	an object of class GenzBretz , Miwa or TVPACK specifying both the algorithm to be used as well as the associated hyper parameters.
...	additional parameters (currently given to GenzBretz for backward compatibility issues).

Details

This program involves the computation of multivariate normal probabilities with arbitrary correlation matrices.

Value

The evaluated distribution function is returned with attributes

error	estimated absolute error and
msg	status messages.

See Also

[dcmvnorm](#), [rcmvnorm](#), [pmvnorm](#).

Examples

```
n <- 10
A <- matrix(rnorm(n^2), n, n)
A <- A %**% t(A)

pcmvnorm(lower=-Inf, upper=1, mean=rep(1,n), sigma=A, dependent.ind=3,
  given.ind=c(1,4,7,9,10), X.given=c(1,1,0,0,-1))

pcmvnorm(lower=-Inf, upper=c(1,2), mean=rep(1,n), sigma=A,
  dep=c(2,5), given=c(1,4,7,9,10), X=c(1,1,0,0,-1))
```

```
pcmvnorm(lower=-Inf, upper=c(1,2), mean=rep(1,n), sigma=A,  
dep=c(2,5))
```

Index

* **distribution**

cmvnorm, 2

condMVN, 3

pcmvnorm, 4

* **multivariate**

cmvnorm, 2

condMVN, 3

pcmvnorm, 4

cmvnorm, 2

condMVN, 3

dcmvnorm, 4, 5

dcmvnorm (cmvnorm), 2

dmvnorm, 2, 4

GenzBretz, 5

Miwa, 5

pcmvnorm, 2, 4, 4

pmvnorm, 2, 4, 5

qmvnorm, 2, 4

rcmvnorm, 5

rcmvnorm (cmvnorm), 2

TVPACK, 5